

MiContact Center Enterprise

Nuance Software Installation Guide (ASR & TTS)

Release 9.6

Document Version 1.0

September 2022



Notices

The information contained in this document is believed to be accurate in all respects but is not warranted by **Mitel Networks**TM **Corporation (MITEL**[®]**).**

The information is subject to change without notice and should not be construed in any way as a commitment by Mitel or any of its affiliates or subsidiaries. Mitel and its affiliates and subsidiaries assume no responsibility for any errors or omissions in this document. Revisions of this document or new editions of it may be issued to incorporate such changes. No part of this document can be reproduced or transmitted in any form or by any means - electronic or mechanical - for any purpose without written permission from Mitel Networks Corporation.

Trademarks

The trademarks, service marks, logos and graphics (collectively "Trademarks") appearing on Mitel's Internet sites or in its publications are registered and unregistered trademarks of Mitel Networks Corporation (MNC) or its subsidiaries (collectively "Mitel") or others. Use of the Trademarks is prohibited without the express consent from Mitel. Please contact our legal department at legal@mitel.com for additional information. For a list of the worldwide Mitel Networks Corporation registered trademarks, please refer to the website: http://www.mitel.com/trademarks.

®,™ Trademark of Mitel Networks Corporation

© Copyright 2022, Mitel Networks Corporation All rights reserved

Introduction	1
Nuance SW download	1
ASR and TTS	5
Supported Languages	5
Deployment Scenarios	6
Single Server and Multiple Clients	6
Single Server and Single Client	6
Installation Preparation	6
Removing Previous Versions of Nuance Software	6
Installing Nuance Software	7
Prepare Server	7
Install Java JDK	7
Install Apache Tomcat	7
Database	7
Install SQL 2019 (SQL 2014 SP1 or 2016 SP2 are also supported)	8
Install MySQL 5.7 and Connector/J	18
Install NSS 11	26
Finish up the installation	32
License configuration	32
OAS	32
TAS	32
Nuance Speech Server	32

Introduction

This document describes the installation process for Nuance software that is used with Open Application Server (OAS) or Telephony Application Server (TAS).

In OAS and TAS, Automatic Speech Recognition (ASR) and Text-to-Speech (TTS) functionality is provided by:

- Nuance Speech Suite 11, which consists of:
 - Nuance License Manager
 - Nuance 11 (ASR)
 - Nuance Vocalizer for Network 7 (TTS)
 - Nuance Management Station

Nuance SW download

There are three packages of Nuance SW available for MiCC Enterprise at the SW download (SWDL) site on the MiAccess portal:

- 1. The base Nuance Speech Server (NSS) 11 package. This includes SW and Nuance documentation in order to install the NSS server and it also includes the US English ASR and TTS language files.
- 2. Nuance Recognizer package. This includes the Recognizer 10 languages for:
 - a. ar-WW Arabic-WorldWide
 - b. ca-ES_Catalan-Spain
 - c. da-DK Danish-Denmark
 - d. de-AT_German-Austria
 - e. de-CH_German-Switzerland
 - f. de-DE_German-Germany
 - g. en-AU_English-Australia
 - h. en-GB_English-United Kingdom
 - i. en-US English-United States
 - i. es-ES Spanish-Spain
 - k. eu-ES_Basque-Spain

- I. fi-FI_Finnish-Finland
- m. fr-BE_French-Belgium
- n. fr-CA French-Canada
- o. fr-FR_French-France
- p. it-IT_Italian-Italy
- q. nl-BE_Dutch-Belgium
- r. nl-NL_Dutch-Netherlands
- s. no-NO_Norwegian-Norway
- t. pl-PL_Polish-Poland
- u. pt-BR_Portuguese_Brazil
- v. ru-RU_Russian-Russian Federation
- w. sv-SE_Swedish-Sweden
- 3. Nuance Vocalizer Packages. The following languages and voices are included:
 - a. ar-WW_Arabic-WorldWide
 - i. Female voice Laila
 - ii. Male voice Tarik
 - b. ca-ES_Catalan-Spain
 - i. Female voice Montserrat
 - ii. Male voice Jordi
 - c. da-DK_Danish-Denmark
 - i. Female voice Sara
 - ii. Male voice Magnus
 - d. de-DE_German-Germany
 - i. Female voice Petra

- ii. Male voice Markus
 e. en-AU_English-Australia
 i. Female voice Karen
 - ii. Male voice Lee
- f. en-GB_English-British-English
 - i. Female voice Stephanie
 - ii. Male voice Oliver
- g. en-US_English-United States (also included in NSS SW package)
 - i. Female voice Zoe
 - ii. Male voice Nathan
- h. es-ES_Spanish-Spain
 - i. Female voice Monica
 - ii. Male voice Jorge
- i. eu-ES_Basque-Spain
 - i. Female voice Miren
- j. fi-FI_Finnish-Finland
 - i. Female voice Satu
 - ii. Male voice Onni
- k. fr-FR_French-France
 - i. Female voice Aurelie
 - ii. Male voice Thomas
- I. it-IT_Italian-Italy
 - i. Female voice Paola
 - ii. Male voice Luca

- m. nl-BE_Dutch-Belgium
 - i. Female voice Ellen
- n. nl-NL Dutch-Netherlands
 - i. Female voice Claire
 - ii. Male voice Xander
- o. no-NO_Norwegian-Norway
 - i. Female voice Nora
 - ii. Male voice Henrik
- p. pl-PL_Polish-Poland
 - i. Female voice Zosia
 - ii. Male voice Krysztof
- q. pt-BR_Portuguese_Brazil
 - i. Female voice Luciana
 - ii. Male voice Felipe
- r. ru-RU Russian-Russian Federation
 - i. Female voice Milena
 - ii. Male voice Yuri
- s. sv-SE_Swedish-Sweden
 - i. Female voice Alva and Klara
 - ii. Male voice Oskar

If another language or TTS voice is needed, then contact Mitel Support to have it downloaded from the Nuance partner portal. For a complete list of languages and TTS voices use the links provided in the section SUPPORTED LANGUAGES below.

ASR and TTS

ASR and TTS software can be installed on multiple servers for load sharing and balancing purposes.

NOTE: According to the Nuance Installation Guide, the following must be considered: "The Speech Suite installer includes one language and one text-to-speech voice. Optionally, you can enable a multilingual system that supports applications in different languages by downloading, installing, and configuring additional languages and voices to a **separate**, dedicated host."

To install an ASR and a TTS language on a single server during the NSS installation copy the extracted language installation packages under the install_language folder in the setup_files folder prior to running the NSS installer. By default the US English ASR and TTS packages are located there.

Supported Languages

Nuance Recognizer ASR Languages

Nuance Vocalizer 7 TTS Languages

The standard library offers 53 languages/dialects and 120 voices, 20 of which are multi-lingual. A complete list of these can be found here.

Deployment Scenarios

It is recommended to install Nuance Speech Server on a separate server as it consumes a lot of CPU usage and memory. The following to deployments can be used:

Single Server and Multiple Clients

In this deployment, only one Nuance Speech Server is installed, and multiple clients (IPMS inside OAS server and standalone IPMS servers or TAS server(s)) connect to it for sending ASR and TTS requests.

Single Server and Single Client

In this deployment, only one Nuance Speech Server is installed, and only one client (IPMS inside OAS, standalone IPMS server or single TAS server) connects to it for sending ASR and TTS requests.

Installation Preparation

Before installing the Nuance software, make sure the following is true:

- You have local administrator privileges.
- You have access to the Nuance installation SW.
- There is no previously installed Nuance software on the server

If a previous version of the software exists, it has to be un-installed first.

Removing Previous Versions of Nuance Software

Any existing installation of the following software needs to be removed:

- Nuance 8.5 or 9.0
- Nuance Additional ASR Languages
- Nuance Vocalizer
- ScanSoft RealSpeak (only present if Nuance 8.5 was installed)
- TTS Language Voices

To check if previous versions of the software exist, do the following:

- 1. Go to Start > Settings > Control Panel, and then click Add/Remove Programs.
- 2. If any of the programs listed above appears in the list of programs, a previous version of that software is installed.

To uninstall previous versions of Nuance software, do the following:

- 1. Close all applications.
- 2. Shut down OAS by double-clicking the <code>OASShutDown.exe</code> application located in the <code>MitelOAS\Bin</code> folder, or shutdown the TAS server(s) if your system is TAS based

- 3. From the Start Menu, select Settings > Control Panel > Services.
- **4.** When the Services applet opens, select the **Nuance Watcher Daemon** service and click the **Stop** button on the tool bar.
- 5. On the Start menu, select Settings > Control Panel. > Add/Remove Programs.
- 6. The Control Panel screen appears.
- 7. Click the software to remove (for example Nuance v8.5).
- 8. Click Change/Remove to remove the previous version of software.
- 9. Click Yes to confirm.
- 10. The system removes the software.
- 11. Repeat steps 6 to 8 for each software package with older version.
- 12. Restart the system.

Installing Nuance Software

Prepare Server

Extract the downloaded file 'Nuance 11.08 setup files.zip' to a temp folder.

Firewall should be turned off.

Ensure that 8.3 file naming is enabled if installing on other than boot drive (C:). Install VC++ 2015-2019 by running *vc_redist.x64.exe* in the 2015-2019 VC++ runtime folder.

NOTE: <u>Carefully</u> follow the instructions in the *Nuance_Speech_Suite-11.0.8-Installation_Guide.pdf* guide that is included together with the NSS installation package. Also carefully note the supported versions of the 3rd party components as stated in the *NSS 11.08 Release Notes.html* document.

Install Java JDK

Run zulu8.40.0.25-ca-jdk8.0.222-win_x64.msi located in the '3rd party files' folder. Accept all Defaults.

Install Apache Tomcat


Extract the content of *apache-tomcat-9.0.22-windows-x64.zip* located in the '3rd party files' folder to e.g. C:\


Remember this location for later NSS installation..


Database


If using SQL Server continue here. If using MySQL then continue at section 'Install MySQL 5.7 and Connector/J' further down in the document.


Install SQL 2019 (SQL 2014 SP1 or 2016 SP2 are also supported)

















Install latest update for SQL Server 2019:

The latest update for SQL Server 2019(currently CU9) can be downloaded from here.

Install SQL Management Studio:

The latest version of the SQL Management Studio (SSMS-Setup-ENU.exe) can be downloaded from here.



Copy sqljdbc42.jar from the ..\3rd party files\SQL Server Connectors folder to e.g. c:\sqljdc_6.0\

Remember file location for later NSS installation.

Install the ODBC Driver 17 by running msodbcsql.msi located in the ..\3rd party files\SQL Server Connectors folder:

<Reboot the server>

Create SQL user ms by opening a Command window and run command sqlcmd -U salogin -P saPassword -S hostname\dbinstancename or just:

sqlcmd -U salogin -P saPassword -S hostname if default instance is used.

Then run commands:

```
1> CREATE LOGIN ms WITH PASSWORD = 'msp', CHECK_POLICY = OFF; 2> go
```

```
Add the dbcreator and bulkadmin roles to the 'ms' user: 1>SP_ADDSRVROLEMEMBER 'ms', 'dbcreator'; 2>go 1>SP_ADDSRVROLEMEMBER 'ms', 'bulkadmin'; 2>go 1>quit
```

Note: The bulkadmin role must be added as well (documentation error in the Nuance installation guide)

Create the mserver database: Log in to SQL Server as the newly created user 'ms' and issue command:

sqlcmd -U ms -P msp -S hostname\dbinstancename or just:

sqlcmd -U ms -P msp -S hostname if default instance is used.

Then run commands: 1> create database mserver; 2> go 1> quit

Create tables in the mserver database by running the script create-tables-sqlserver.sql.


Open a cmd window (Run as Administrator) and go to folder \Setup_files\NSS\Nuance_Speech_Suite-11.0.8\external_db_scripts and **Run** the command sqlcmd -U ms -P msp -d mserver -i create-tables-sqlserver.sql


```
Administrator Command Prompt


C:\setup_files\NSS\Nuance_Speech_Suite-11.0.8\external_db_scripts>sqlcmd -U ms -P msp -d mserver -i create-tables-sqlser ver.sql


(1 rows affected)
```


Create the ODBC data source MSERVER






















Continue at 'Install NSS 11.08' below.


Install MySQL 5.7 and Connector/J


Run *mysql-installer-community-5.7.30.0.msi* located in the *3rd party filesWySQL* folder and select Custom and then select these items:


(Note that Connector/C will be installed by selecting MySQL Server)




















Create user 'ms' using the MySQL Client. Issue commands:

```
mysql> CREATE USER 'ms'@'localhost' IDENTIFIED WITH MYSQL_NATIVE_PASSWORD BY 'msp';
mysql > GRANT ALL PRIVILEGES ON *.* to 'ms'@'localhost' WITH GRANT OPTION;
mysql > FLUSH PRIVILEGES;
mysql > SELECT create_priv FROM mysql.user WHERE user='ms' AND host='localhost';
```

Create database mserver and its tables: Copy create-tables.sql to C:\Program Files\MySQL\MySQL Server 5.7\bin


Run MySQL client and issue commands:

```
mysql> create database mserver;
mysql> use mserver;
mysql> source create-tables.sql;
```


```
Query OK, 0 rows affected (0.05 sec)
```

Configure database performance:


Stop the MySQL service if it is running:



Open *C:\ProgramData\MySQL\MySQL Server 5.7\my.ini* in **Wordpad** and set character-set-server=latin1



Change table_open_cache to be 512




Save the file as 'Plain text document'. If using Notepad then the MySQL service will not start...

Delete the ib_logfile* files located in C:\ProgramData\MySQL\MySQL Server 5.7\data folder.

<Reboot the Server>


Use MySQL client to check that the ms user exists and has create_priv privileges. Issue commands:

mysql> use mysql; mysql> select create_priv, user, host from user;




Install NSS 11


The installation package is available in the *NSS* folder in the temp folder where the installation package was extracted. Right click on '*Nuance Speech Suite 11.0.exe*' and select '*Run as Administrator*'. If all Nuance components are to be installed on this server then select all three components: License Manager, Management Station and Speech Software:




Enter the location of the Nuance License file. It is availabel in the folder *NSS\License* and is named *Nuance_11_ConsolidatedLicenseFile.lic*:




Enter the location of the Java JDK installation:





Select database type. If MS SQL Service is used:






If MySQL is used:










To install the provided US English ASR and TTS languages files then point to the folder *Install_lang* in the folder where the installation package was extracted. Otherwise replace these packages with any language (extracted) from the Recognizeer and Vocalizer packages availabe on SWDL.

If SQL server is used then enter the path to the *msodbcsql17.dll* file that typically is installed in the *C:\Windows\System32* folder.

If MySQL is used the point to the *libmysql.dll* file in the *<drive>:\Program Files\MySQL\MySQL Server 8.0\lib* folder.







Finish up the installation

Copy updated NSSserver.cfg file from the SpeechServer_config folder to <Drive>:\Program Files (x86)\Nuance\Speech Server\Server\config

Open Services Control Manager and right mouse click on Nuance Speech Server, select Properties and change Startup type to Automatic (Delayed).

Follow the instruction in the Nuance Installation guide how to log on to the Nuance Management Station (user is *Administrator* and initial password in *changeit*) to assign resources and to start the services.

License configuration

OAS

There is a diffrence in the way Nuance integration is implemented in TAS vs. OAS. When using OAS each OAS Media Server establishes a set number of connections to the Nuance Speech Server at startup. This is configured in the 'AsrTtsObjects" variable in the hlink.cfg file located in the *<OAS installation folder>/bin* folder. This variable should typically be set to the highest number of ASR or TTS channel licenses available in the system. But it can also be used in a system where multiple OAS Media Servers are used, so that it can be controlled how many concurrent Nuance ASR and/or TTS sessions that can be performed per media server.

TAS

For TAS servers there is no configuration files to update since TAS does not establish a set number of connections at startup. TAS initiates SIP sessions dynamically to Nuance Speech Server when speech resources are requested and tears down thew session when the call is completed.

Nuance Speech Server

Nuance Speech Server does by default only accept 4 simultaneous sessions for ASR and/or TTS. To specify the maximum number of ASR sessions then the variable 'swirec_license_ports' in the file 'User-nrs01.xml' located in the C:\ProgramData\Nuance\Enterprise\system\config folder must be set to match the number of concurrent ASR sessions this Nuance server is to handle.

In the same manner, the number of concurrent TTS sessions is specified in the variable 'tts_license_ports' in the file 'User-nvs01.xml' located in the

C:\ProgramData\Nuance\Enterprise\system\config folder. This should be set to the highest number of concurrent TTS sessions to be handled by this Nuance server.

